


## NETWORK LICENSE

### HOW TO INSTALL NETWORK LICENSE


The following page introduces the step by step to install network license.

#### 1 NEW INSTALLATION (LICENSE SERVICE ON SERVER)


- Log on to the computer with hostid which lists in the license file
- Save the enclosed license file in C:\Flexlm. Create this folder if it does not exist.
- Download and install the latest version of license manager, either from NH package or download separately from <https://sesam.dnv.com/download/programs.html>.
- Installing will set up and automatically start a license service.
  - 1) Double click setup.exe to install license manager




- 2) The latest license manager requires Microsoft Visual C++ 2017 Redistributable, if your computer hasn't installed it before, below dialog will pop up, click **Install**. If no this dialog shows, just skip this step.




- 3) Continue the license manager installation step by step




If you want to install license manager at another folder, click change button to point out, otherwise click **Next** to continue.




If you have dongle license need to be used later, you can tick 'USB dongle driver for FLEXID 9' to install dongle driver here. Otherwise, just click 'Next' to continue.




Next step will set environment variable in the OS. The default port number is 2002 which also can find the license file. Click **Next** to continue.




Click **Install**.




Click **Finish** to complete the installation.




Launch license manger from windows start menu.



In the **Config Services** tab, click **View Log** button.



In the log, go down to the bottom. If it looks like below and there is no any sever shut down information, the server is installed successfully.



## 2 NEW INSTALLATION (CLIENT MACHINES)

Client machines only require a system environment variable pointing to the port number and server name of the licensing service.

**DNVSLM\_LICENSE\_FILE = 2002@name-of-the-license-server**

Or

**DNVSLM\_LICENSE\_FILE = 2002@ip-address-of-the-license-server**

Refer the document in the same web page: [How to set environment variable to connect to network license server?](#)

If client machine cannot connect license server successfully, refer [How to Check Firewall Communication?](#)

Author: Li Zheng Nan Anna, April 1<sup>st</sup>, 2020 Updated: July, 30<sup>th</sup>, 2024

DNV Headquarters, Veritasveien 1, P.O.Box 300, 1322 Høvik, Norway. Tel: +47 67 57 99 00. [www.dnv.com](http://www.dnv.com)